


Windows 7 64 bit Driver Update


Objective: To update your Windows 7 64 bit operating system with a compatible iTrail driver. This update will only work with Windows 7 64 bit operating system.

- Unzip the Win 7 64 Bit Driver
- Right click Install and select “Run as Administrator”



- Click Install Device Driver






- After the driver is installed a window will pop up asking if you would like to install the device software. Click install.




- A message will appear asking you to connect the logger to PC USB port.




- In the installation process the system tray in the bottom right will show the installation is proceeding.



- GPS Logger USB Port (COM3) will show up in the bottom right corner after the installation is finished.



- Operation system will the program compatibility for the driver. Select “This program is installed correctly”




Verification:


- In order to check if the driver was installed correctly, click Start then Control Panel.
- Click System and Security



- Click “Device Manager” under System



- Make sure “GPS Logger USB COM” shows up within Ports



- Verification is now complete